



# **Aras Innovator**

## Applying Hotfix 016146



Aras Innovator 9.3 Document #: 9.3.008012011 Last Modified: 8/2/2011



Aras Corporation

All Rights Reserved.

### **ARAS CORPORATION**

Copyright © 2011 Aras Corporation. All rights reserved

Aras Corporation 300 Brickstone Square Suite 904 Andover, MA 01810

Phone: 978-691-8900 Fax: 978-794-9826

E-mail: Support@aras.com Website: http://www.aras.com

#### **Notice of Rights**

Copyright © 2011 by Aras Corporation. This material may be distributed only subject to the terms and conditions set forth in the Open Publication License, V1.0 or later (the latest version is presently available at http://www.opencontent.org/openpub/).

Distribution of substantively modified versions of this document is prohibited without the explicit permission of the copyright holder.

Distribution of the work or derivative of the work in any standard (paper) book form for commercial purposes is prohibited unless prior permission is obtained from the copyright holder.

Aras Innovator, Aras, and the Aras Corp "A" logo are registered trademarks of Aras Corporation in the United States and other countries.

All other trademarks referenced herein are the property of their respective owners.

#### **Notice of Liability**

The information contained in this document is distributed on an "As Is" basis, without warranty of any kind, express or implied, including, but not limited to, the implied warranties of merchantability and fitness for a particular purpose or a warranty of non-infringement. Aras shall have no liability to any person or entity with respect to any loss or damage caused or alleged to be caused directly or indirectly by the information contained in this document or by the software or hardware products described herein.



### **Table of Contents**

1	OVERVIEW	5
2	PREREQUISITES	6
	2.1 CHECKING FOR ELIGIBILITY	6
	2.2 REQUIRED TOOLS AND MATERIALS	
	2.2.1 Package Import Export Utilities	8
	2.2.2 Aras Innovator Hotfix 016146 Patch	8
3	UPGRADE PROCESS	9
	3.1 UPGRADING THE PRODUCTION INSTANCE	9
	3.1.1 Notification and Backup	9
	3.1.2 Applying the Patch	10
	3.1.3 Confirming the Patch	13
	3.1.4 Testing Your Upgrade	13
4	APPENDIX	14
	4.1 Hotfix 016146	
	4.1.1 Issues Fixed in Hotfix 016146	14



### 1 Overview

The hotfix outlined in this document is intended to enhance the Aras Innovator Product Engineering solution to better support CAD integrations with Aras Innovator.

The steps outlined in this document describe how to apply the hotfix to Aras Innovator 9.3.0, only. The enhancements made in this hotfix are seen as "core" and "solutions" changes from the Aras Innovator 9.3.0 platform. These changes affect both the database and the code tree. If you feel that you cannot apply the hotfix yourself after reading this document, subscribers may contact Aras Support at <a href="mailto:support@aras.com">support@aras.com</a>.



### 2 Prerequisites

In order to apply the hotfix to Aras Innovator 9.3.0, you will need to first check that your software is currently eligible. Then you will need to download the necessary materials for upgrade.

### 2.1 Checking for Eligibility

Please use the following steps to check if your code tree and database are eligible to apply the hotfix.

- 1) Log in to Aras Innovator as an administrator
- 2) From the Main Menu select Help→About
- 3) Confirm that the dialog shows the following:
  - a. Aras Innovator 9.3.0 Build 5663



- 4) Close the dialog.
- 5) From the TOC, select Administration\Variables



6) Confirm that the following sets of variables are listed:

	Version	Version	Version	Version
	Major	Minor	ServiceUpdate	ServicePack
9.3.0	9	3	0	None

If you do not meet the hotfix requirements listed in the previous steps, then you should contact Aras to discuss your options.



### 2.2 Required Tools and Materials

If you have successfully met the requirements in the <u>Prerequisites</u> section, then the next step is to obtain the required upgrade files and utilities.

### 2.2.1 Package Import Export Utilities

The first thing you will need is the Package Import Export utilities. The open version of this tool can be found on the Aras community projects website. Subscribers can obtain the latest version of this tool from the Aras FTP site.

### 2.2.2 Aras Innovator Hotfix 016146 Patch

The next thing you will need is the Hotfix 016146 patch. This patch can be downloaded from the Aras community projects website. It is recommended a copy of the patch contents be put on the web server for direct application of code tree components.



### 3 Upgrade Process

This section will walk you through applying Hotfix 016146 to Aras Innovator 9.3.0. Aras recommends you do a test run of Hotfix 016146 on a non-production instance, before attempting this upgrade on your production system.

### 3.1 Upgrading the Production Instance

Applying the hotfix to a production instance of Aras Innovator should be done with planning of a short timetable, and an ability to back out the upgrade if something in the process unexpectedly fails.

The following sections are a rough outline of the steps used when upgrading the Aras Innovator production instance.

#### 3.1.1 Notification and Backup

- 1) Notify users the system will be down at a scheduled time, and that they should log out of the system prior to the start of the process.
  - a. It is best to give at least 24 hours notice, as well as a reminder 15 minutes prior to the upgrade.
- 2) Back up the code tree:

The "Code Tree" refers to files and folders installed to the disk when Aras Innovator was first installed.

The default path for the Code Tree installation would be something similar to:

C:\Program Files\Aras\Innovator

#### With the following contents:

Name	Size	Туре 🔺
🛅 DB		File Folder
🛅 Innovator		File Folder
🚞 Install		File Folder
🚞 VaultServer		File Folder
🖭 InnovatorServerConfig.xml	2 KB	XML Document
🔮 VaultServerConfig.xml	1 KB	XML Document

You can confirm the installation folder with the following steps:

- a. From the Start Menu, select Start→Setting→Control Panel
- b. From the Control Panel, select Add/Remove Programs
- c. Search for the Aras Innovator entry in the Add/Remove Programs window
- d. Select the "Click here for support information." link in the Aras Innovator entry



🐻 Support Info	
Aras Innovato	r
Use the following Aras Innovator	information to get technical support for
Publisher: Version:	Aras Corporation 9.2.0
Comments:	Installed to C:\Program Files\Aras\Innovator\
	Close

Once you have determined where the code tree is installed, you will want to backup the folder and all of its contents.

- 3) Disconnect all users from the database
  - a. The easiest way to prevent client sessions from committing any further changes to the database is to change the database connection string in the InnovatorServerConfig.xml from "<DB-Connection..." to <xDB-Connection" and restart the w3svc service(IIS). This will expire all session and prevent all new connections to the Aras Innovator database through the existing instance.
- 4) Backup the database.
  - a. Place this file in a safe location, as it will be necessary to restore from it if the upgrade fails.
- 5) Enable database connections
  - After your database backup has completed, you can enable the database connection string in the InnovatorServerConfig.xml by simply changing it from "<xDB-Connection..." to <DB-Connection" and restarting the w3svc service(IIS).</li>

### 3.1.2 Applying the Patch

1) Unzip the "Hotfix016146.zip" file on the server.



- 2) Copy the \Innovator folder to the root of your install directory, overwriting the existing \Innovator folder and all its contents.
  - a. It is recommended that this step be performed by an administrator on the server.

Confirm F	older Replace	×
<b>5</b>	This folder already contains a folder named 'Innovator'. If the files in the existing folder have the same name as files in the folder you are moving or copying, they will be replaced. Do you still want to move or copy the folder?	
	Yes to <u>All</u> <u>N</u> o Cancel	



- 3) Copy the \VaultServer folder to the root of your install directory, overwriting the existing \VaultServer folder and all its contents.
  - a. It is recommended that this step be performed by an administrator on the server.

		_
Confirm F	older Replace	×
1	This folder already contains a folder named 'VaultServer'. If the files in the existing folder have the same name as files in the folder you are moving or copying, they will be replaced. Do you still want to move or copy the folder?	
	Yes to <u>All</u> <u>N</u> o Cancel	



- 4) Next you will need to import the database package with the Package Import Export Utilities (For more information using this tool, please see the *Aras Innovator 9.3* -*Package Import Export Utilities* documentation.)
  - a. You will need to enable the "Super User" login to perform this step.
  - b. Browse to the \PackageImportExportUtilities\Import\ folder and run the Import.exe file

者 Import			
Import Exit Abo	) ut		
☐Innovator Ser Server: Database: Username: Password:	ver	Release settings TargetRelease: 9.3.0 Description: Hotfix 016146	
Manifest File Path:	C:\Hotfix016146\Imports\imports.mf		
Available for Import      Available for Import     Image: com.aras.innovator.core     Image: com.aras.innovator.solution.PLM     Image: com.aras.innovator.solution.plm <			

- c. Input the connection information
  - i. Server = The connection URL for Aras Innovator
  - ii. Database = The target Aras Innovator 9.3.0 database
  - iii. Username = root
  - iv. Password = Password for "root" login (Default is "innovator")
  - v. Target Release = 9.3.0
  - vi. Description = Hotfix 016146
  - vii. Manifest File Path = The manifest is found in the unzipped patch folder in \Imports\imports.mf
  - viii. Available for Import = Check "com.aras.innovator.core"
    - "com.aras.innovator.solutions.PLM"
    - ix. Type = Merge
    - x. Mode = Thorough Mode
- d. Select Import from the utility



Note: Please remember to disable the "Super User" login once complete. This login should not be enabled in production.

### **3.1.3 Confirming the Patch**

Please use the following steps to check if your code tree and database have applied the hotfix to Aras Innovator 9.3.0.

- 1) Log in to Aras Innovator as an administrator
- 2) From the Main Menu select  $Help \rightarrow About$
- 3) Confirm that the dialog shows the following:
  - a. Aras Innovator 9.3.0 Build 5670

About Aras Innovator Webpage Dialog
aras INNOVATOR®
Aras Innovator Version 9.3.0 Build: 5670
For support please go to <a href="http://www.aras.com/support/">http://www.aras.com/support/</a> .
Visit us on-line at <u>http://www.aras.com</u> .
© 2000-2011 Aras Corporation. Portions Copyright 1997-2005 WinMain Software, Inc. All rights reserved.
OK

- 4) Close the dialog.
- 5) From the TOC, select Administration\Variables
- 6) Confirm that following variables are listed:

VersionMajor	VersionMinor	VersionServiceUpdate	VersionServicePack	IR-016146
9	3	0	None	Patched

If any part of this test fails, please revert to your backups and contact Aras Support at <a href="mailto:support@aras.com">support@aras.com</a>.

#### 3.1.4 Testing Your Upgrade

Aras recommends you test any critical functionality before going live with any upgrade

- Test critical functionality
- Test the vault
  - Add a new file, view that file, and finally delete that file.
  - View existing file from prior to the upgrade.

If all tests are satisfactory, notify users the system is running again.

### 4.1 Hotfix 016146

Aras Innovator Hotfix 016146 contains core and solutions fixes.

### 4.1.1 Issues Fixed in Hotfix 016146

### Framework

Required	Issue #	Description
Yes	015868	Addressed recursion error in the GetItemRepeatConfig action.
Yes	015971, 016146, 016136	Metadata model updates to improve support of CAD integrations. Introduces configuration handling for part families defined in CAD systems and new load options for retrieving files from Aras Innovator into CAD systems.

